

# CanoPy user manual

CanoPy is the Python module for [the Georgia Canopy Analysis 2009 project](#) sponsored by [the Georgia Forestry Commission \(GFC\)](#). For further information about this project, please refer to the [CanoPy page](#).

This document explains how to use the [CanoPy](#) module. For technical details, please read the [CanoPy technical manual](#). Also refer to the [CanoPy tutorial](#).

## Authors

- [Huidae Cho, Ph.D., GISP, PE \(MD\), CFM, M.ASCE, Ph.D.](#)
- [Owen Smith](#)

## Requirements

- ArcGIS Desktop 10.x
- ArcPy
- Python 2 standard module: os
- Feature Analyst™ by the Textron Systems
- Automated Feature Extraction (AFE) models trained using Feature Analyst

We are currently planning on developing a fully open source solution without using ArcGIS and Feature Analyst.

## How to use the CanoPy module

1. Clone the [CanoPy GitHub repository](#)

```
git clone https://github.com/HuidaeCho/canopy.git
```

2. Copy `canopy_config-example.py` to `canopy_config.py`
3. Edit `canopy_config.py` to recognize your layers and folder structures
4. Start ArcMap
5. Add `Physiographic_Districts_GA.shp`. Its layer name is `phyregs_layer` in `canopy_config.py`
6. Add `naip_ga_2009_1m_m4b.shp`. Its layer name is `naipqq_layer` in `canopy_config.py`
7. Open the Python window from within ArcMap
8. Import the canopy module

```
import sys
sys.path.append('C:/path/to/the/canopy/module')
import canopy
```

9. Assign physiographic region IDs to the `naipqq` layer

```
canopy.assign_phyregs_to_naipqq()
```

10. Add physiographic region IDs to process to phyreg\_ids

```
phyreg_ids = [8, 7]
```

11. Reproject original NAIP QQ tiles to the target projection

```
canopy.reproject_naip_tiles(phyreg_ids)
```

12. Run trained AFE models to classify canopy and non-canopy cells

13. Convert AFE output files to the final seamless canopy GeoTIFF file per physiographic region

```
canopy.convert_afe_to_canopy_tiff(phyreg_ids)
```

[software](#)

From:  
<https://hydrowiki.isnew.info/> - **HydroCS Wiki**

Permanent link:  
[https://hydrowiki.isnew.info/software/canopy/user\\_manual](https://hydrowiki.isnew.info/software/canopy/user_manual)

Last update: **2024-08-03 10:43 pm**

